

EDITAR WLANS Y SUS CONTRASEÑAS EN VIRTUAL ZONE DE RUCKUS

Una vez dentro del sistema de virtual zone, dirigirse a Wireless LAN.




FIG.1 Wireless LAN

Dentro de esa opción, dirigirse a la pestaña “configuration” y dar click en “configure” en ese apartado se puede crear la WLAN y/o modificar sus parámetros, tales como la contraseña .





FIG 2. Selección de la organización y pestaña de configuración.

Área Diseño LAN		Título/Tema CAMBIO DE CONTRASEÑA WLAN		Documento Instructivo_virtualzone_wlans.pdf	
Elaboró Daniel Sánchez	Revisó Andrés Arizpe	Fecha 37 Abril 2019	Versión 1.0	Pág. 1	

Dentro de esta opción y como se muestra a continuación es posible editar los parámetros correspondientes a la red WLAN (Wireless)


Edit WLAN Config: 3RIOS Intranet



The screenshot shows the 'Edit WLAN Config: 3RIOS Intranet' window. It has a title bar with a close button (X). The window is divided into two main sections: 'General Options' and 'Authentication Options'. In the 'General Options' section, there are fields for 'Name' (3RIOS Intranet), 'SSID' (3riosintranet), 'Description' (empty), 'Zone' (3RIOS-Intranet), and 'WLAN Group' (default). The 'Authentication Options' section shows 'Authentication Type' with radio buttons for 'Standard usage (For most regular wireless networks)', 'Hotspot (WISPr)', 'Guest Access', 'Web Authentication', 'Hotspot 2.0 Access', 'Hotspot 2.0 Onboarding', and 'WeChat'. The 'Method' section has radio buttons for 'Open', '802.1X EAP', 'MAC Address', and '802.1X EAP & MAC'.

FIG 3. Parte superior de la pantalla “configure” opciones generales y opciones de autenticación.

Edit WLAN Config: 3RIOS Intranet



The screenshot shows the 'Edit WLAN Config: 3RIOS Intranet' window, focusing on the 'Encryption Options' section. The 'Authentication Type' and 'Method' sections are visible at the top. The 'Encryption Options' section includes 'Method' (WPA2, WPA-Mixed, WEP-64 (40 bits), WEP-128 (104 bits), None), 'Algorithm' (AES, AUTO), 'Passphrase' (contraseña), '802.11r Fast Roaming' (OFF), '802.11w MFP' (Disabled, Capable, Required), and 'Dynamic PSK' (Disable, Internal, External). At the bottom, there is a 'Data Plane Options' section and a checkbox for 'Access Network' (OFF) with the text 'Tunnel WLAN traffic through Ruckus GRE'. At the bottom right, there are 'OK' and 'Cancel' buttons.

FIG. 4 Pantalla inferior con la opción de “Encryption Options” para cambiar contraseña de la WLAN

Área Diseño LAN		Título/Tema CAMBIO DE CONTRASEÑA WLAN		Documento Instructivo_virtualzone_wlans.pdf	
Elaboró Daniel Sánchez	Revisó Andrés Arizpe	Fecha 37 Abril 2019	Versión 1.0	Pág. 2	